serpentTools Documentation

Release 0.2.1+10.g4211720

The serpentTools developer team

CONTENTS:

1 Welcome!			1		
	1.1	serpent-tools	1		
	1.2	License	2		
2	Exan	nples	3		
	2.1	User Control	3		
	2.2	Branching Reader	6		
	2.3	DetectorReader	10		
	2.4	DepletionReader	20		
3	API		25		
	3.1	Settings	25		
	3.2	Messages	26		
	3.3	Parser Module	27		
	3.4	Parsing Engines	28		
	3.5	Containers	30		
	3.6	Branching Reader	38		
	3.7	Bumat Reader	38		
	3.8	Depletion Reader	39		
	3.9	Detector Reader	39		
	3.10	Fission Matrix Reader	39		
	3.11	Results Reader	40		
	3.12	Samplers	40		
4	Deve	loper's Guide	47		
	4.1	Contributing	47		
	4.2	Data Model	48		
	4.3	Coding Style	49		
	4.4	Documentation	50		
	4.5	Pull Request Checklist	52		
	4.6	Version Control	53		
5	Indic	ees and tables	55		
Ру	thon N	Module Index	57		
In	dex		59		

CHAPTER

ONE

WELCOME!

1.1 serpent-tools

A suite of parsers designed to make interacting with SERPENT¹ output files simple and flawless.

The SERPENT Monte Carlo code is developed by VTT Technical Research Centre of Finland, Ltd. More information, including distribution and licensing of SERPENT can be found at montecarlo.vtt.fi

1.1.1 Installation

The serpentTools package can be downloaded either as a git repository or as a zipped file. Both can be obtained through the Clone or download option at the serpent-tools GitHub.

Once the repository has been downloaded or extracted from zip, the package can be installed with:

```
cd serpentTools
python setup.py install
python setup.py test
```

Installing with setuptools is preferred over the standard distutils module. setuptools can be installed with pip as:

```
pip install -U setuptools
```

Installing in this manner ensures that the supporting packages, like numpy are installed and up to date.

1.1.2 Issues

If you have issues installing the project, find a bug, or want to add a feature, the GitHub issue page is the best place to do that.

1.1.3 Contributors

Here are all the wonderful people that helped make this project happen

- · Andrew Johnson
- Dr. Dan Kotlyar

¹ Leppanen, J. et al. (2015) "The Serpent Monte Carlo code: Status, development and applications in 2013." Ann. Nucl. Energy, 82 (2015) 142-150

- · Stefano Terlizzi
- · Gavin Ridley

1.1.4 References

The Annals of Nuclear Energy article should be cited for all work using SERPENT. If you wish to cite this project, please cite as:

```
url{@serpentTools
    author = {Andrew Johnson and Dan Kotlyar and Stefano Terlizzi and Gavin Ridley},
    title = {serpentTools: A suite of parsers designed to make
    interacting with SERPENT outputs simple and flawless},
    url = {https://github.com/CORE-GATECH-GROUP/serpent-tools},
    year = {2017}
}
```

1.2 License

MIT License

Copyright (c) 2017-2018 Andrew Johnson, Dan Kotlyar, Stefano Terlizzi, GTRC

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

CHAPTER

TWO

EXAMPLES

2.1 User Control

The serpentTools package is designed to, without intervention, be able to store all the data contained in each of the various output files. However, the serpentTools.settings module grants great flexibility to the user over what data is obtained through the rc class. This notebook will provide as an intro into using this class.

2.1.1 Basic Usage

```
>>> import serpentTools
INFO : serpentTools: Using version 0.2.1
>>> from serpentTools.settings import rc, defaultSettings
```

Below are the default values for each setting available

```
>>> for setting in sorted(defaultSettings.keys()):
       print(setting)
       for key in defaultSettings[setting]:
           print('\t', key, '-', defaultSettings[setting][key])
depletion.materialVariables
    default - []
     description - Names of variables to store. Empty list -> all variables.
     type - <class 'list'>
depletion.materials
     default - []
     description - Names of materials to store. Empty list -> all materials.
     type - <class 'list'>
depletion.metadataKeys
    default - ['ZAI', 'NAMES', 'DAYS', 'BU']
     description - Non-material data to store, i.e. zai, isotope names, burnup
\rightarrowschedule, etc.
     type - <class 'list'>
     options - default
depletion.processTotal
     default - True
     description - Option to store the depletion data from the TOT block
     type - <class 'bool'>
serpentVersion
     default - 2.1.29
     description - Version of SERPENT
     type - <class 'str'>
     options - ['2.1.29']
```

(continues on next page)

(continued from previous page)

```
verbosity
    default - warning
    type - <class 'str'>
    description - Set the level of errors to be shown.
    updater - <function updateLevel at 0x000001B7F3DD6598>
    options - ['critical', 'error', 'warning', 'info', 'debug']

xs.variableExtras
    default - []
    description - Full SERPENT name of variables to be read
    type - <class 'list'>
xs.variableGroups
    default - []
    description - Name of variable groups from variables.yaml to be expanded into_
    ⇒SERPENT variable to be stored
    type - <class 'list'>
```

Settings such as depletion.materialVariables are specific for the DepletionReader, while settings that are led with xs are sent to the ResultsReader and BranchingReader, as well as their specific settings. The rc class acts as a dictionary, and updating a value is as simple as

```
>> rc['verbosity'] = 'debug'
DEBUG : serpentTools: Updated setting verbosity to debug
```

The rc object automatically checks to make sure the value is of the correct type, and is an allowable option, if given.

```
>>> try:
... rc['depletion.metadataKeys'] = False
... except TypeError as te:
... print(te)
Setting depletion.metadataKeys should be of type <class 'list'>, not <class 'bool'>
>>> try:
... rc['serpentVersion'] = '1.2.3'
... except KeyError as ke:
... print(ke)
"Setting serpentVersion is
1.2.3
and not one of the allowed options:
['2.1.29']"
```

The rc object can also be used inside a context manager to revert changes.

Group Constant Variables

Two settings control what group constant data and what variables are extracted from the results and coefficient files.

- 1. xs.variableExtras: Full SERPENT_STYLE variable names, i.e. INF_TOT, FISSION PRODUCT DECAY HEAT
- 2. xs.variableGroups: Select keywords that represent blocks of common variables

These variable groups are stored in serpentTools/variables.yaml and rely upon the SERPENT version to properly expand the groups.

```
>>> rc['serpentVersion']
'2.1.29'
>>> rc['xs.variableGroups'] = ['kinetics', 'xs', 'diffusion']
>>> rc['xs.variableExtras'] = ['XS_DATA_FILE_PATH']
>>> varSet = rc.expandVariables()
>>> print(sorted(varSet))
['ABS', 'ADJ_IFP_ANA_BETA_EFF', 'ADJ_IFP_ANA_LAMBDA', 'ADJ_IFP_GEN_TIME',
 'ADJ_IFP_IMP_BETA_EFF', 'ADJ_IFP_IMP_LAMBDA', 'ADJ_IFP_LIFETIME',
'ADJ_IFP_ROSSI_ALPHA', 'ADJ_INV_SPD', 'ADJ_MEULEKAMP_BETA_EFF',
 'ADJ_MEULEKAMP_LAMBDA', 'ADJ_NAUCHI_BETA_EFF', 'ADJ_NAUCHI_GEN_TIME',
 'ADJ_NAUCHI_LAMBDA', 'ADJ_NAUCHI_LIFETIME', 'ADJ_PERT_BETA_EFF',
 'ADJ_PERT_GEN_TIME', 'ADJ_PERT_LIFETIME', 'ADJ_PERT_ROSSI_ALPHA', 'CAPT',
 'CHID', 'CHIP', 'CHIT', 'CMM_DIFFCOEF', 'CMM_DIFFCOEF_X', 'CMM_DIFFCOEF_Y',
 'CMM_DIFFCOEF_Z', 'CMM_TRANSPXS', 'CMM_TRANSPXS_X', 'CMM_TRANSPXS_Y',
 'CMM_TRANSPXS_Z', 'DIFFCOEF', 'FISS', 'FWD_ANA_BETA_ZERO',
 'FWD_ANA_LAMBDA', 'INVV', 'KAPPA', 'NSF', 'NUBAR', 'RABSXS', 'REMXS',
 'SO', 'S1', 'S2', 'S3', 'S4', 'S5', 'S6', 'S7', 'SCATTO', 'SCATT1',
 'SCATT2', 'SCATT3', 'SCATT4', 'SCATT5', 'SCATT6', 'SCATT7', 'TOT',
 'TRANSPXS', 'XS_DATA_FILE_PATH']
```

However, one might see that the full group constant cross sections are not present in this set

```
>>> assert 'INF_SCATT3' not in varSet
```

This is because two additional settings instruct the <code>BranchingReader</code> and <code>ResultsReader</code> to obtain infinite medium and leakage-corrected cross sections: <code>xs.getInfXS</code> and <code>xs.getB1XS</code>, respectively. By default, <code>xs.getInfXS</code> and <code>xs.getB1XS</code> default to True. This, in conjunction with leaving the <code>xs.variableGroups</code> and <code>xs.variableExtras</code> settings to empty lists, instructs these readers to obtain all the data present in their respective files.

See the Branching Reader example for more information on using these settings to control scraped data.

Configuration Files

As of version 0.1.2, the rc object allows for settings to be updated from a yaml configuration file using the <code>loadYaml()</code> method. The file is structured with the names of settings as keys and the desired setting value as the values. The loader also attempts to expand nested settings, like reader-specific settings, that may be lumped in a second level.

```
verbosity: warning
xs.getInfXS: False
branching:
    areUncsPresent: False
    floatVariables: [Fhi, Blo]
depletion:
    materials: [fuel*]
    materialVariables:
    [ADENS, MDENS, VOLUME]
```

2.1. User Control 5

2.2 Branching Reader

This notebook demonstrates the capability of the serpentTools package to read branching coefficient files. The format of these files is structured to iterate over:

- 1. Branch states, e.g. burnup, material properties
- 2. Homogenized universes
- 3. Group constant data

The output files are described in more detail on the SERPENT Wiki

2.2.1 Basic Operation

The simplest way to read these files is using the <code>serpentTools.parsers.read()</code> function

Note: Without modifying the settings, the *BranchingReader* assumes that all group constant data is presented without the associated uncertainties. See *User Control* for examples on the various ways to control operation

```
>>> import serpentTools
>>> branchFile = 'demo.coe'
INFO : serpentTools: Using version 0.2.1
>>> r0 = serpentTools.read(branchFile)
INFO : serpentTools: Inferred reader for demo.coe: BranchingReader
INFO : serpentTools: Preparing to read demo.coe
INFO : serpentTools: Done reading branching file
```

The branches are stored in custom BranchContainer objects in the branches dictionary

```
>>> r0.branches
{('B1000', 'FT1200'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c762438>,
 ('B1000', 'FT600'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c787908>,
 ('B1000', 'nom'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c737ef0>,
 ('B750', 'FT1200'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c752cf8>,
 ('B750', 'FT600'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c77c208>,
 ('B750', 'nom'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c72c860>,
 ('nom', 'FT1200'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c7455f8>,
 ('nom', 'FT600'):
   <serpentTools.objects.containers.BranchContainer at 0x2220c76dac8>,
 ('nom', 'nom'):
    <serpentTools.objects.containers.BranchContainer at 0x2220c7231d0>}
```

Here, the keys are tuples of strings indicating what perturbations/branch states were applied for each SERPENT solution. Examining a particular case

```
>>> b0 = r0.branches['B1000', 'FT600']
>>> print(b0)
<BranchContainer for B1000, FT600 from demo.coe>
```

SERPENT allows the user to define variables for each branch through:

```
var V1_name V1_value
```

cards. These are stored in the stateData attribute

```
>>> b0.stateData
{'BOR': '1000',
    'DATE': '17/12/19',
    'TFU': '600',
    'TIME': '09:48:54',
    'VERSION': '2.1.29'}
```

The keys 'DATE', 'TIME', and 'VERSION' are included by default in the output, while the 'BOR' and 'TFU' have been defined for this branch.

Group Constant Data

Note: Group constants are converted from SERPENT_STYLE to mixedCase to fit the overall style of the project.

The BranchContainer stores group constant data in HomogUniv objects in the universes dictionary

```
>>> b0.universes
{(0, 0.0, 1): <serpentTools.objects.containers.HomogUniv at 0x2220c781ac8>,
(0, 1.0, 2): <serpentTools.objects.containers.HomogUniv at 0x2220c78b5f8>,
(0, 10.0, 3): <serpentTools.objects.containers.HomogUniv at 0x2220c791240>,
(10, 0.0, 1): <serpentTools.objects.containers.HomogUniv at 0x2220c787a58>,
 (10, 1.0, 2): <serpentTools.objects.containers.HomogUniv at 0x2220c78b6a0>,
 (10, 10.0, 3): <serpentTools.objects.containers.HomogUniv at 0x2220c791320>,
 (20, 0.0, 1): <serpentTools.objects.containers.HomogUniv at 0x2220c787cc0>,
 (20, 1.0, 2): <serpentTools.objects.containers.HomogUniv at 0x2220c78b908>,
 (20, 10.0, 3): <serpentTools.objects.containers.HomogUniv at 0x2220c791588>,
 (30, 0.0, 1): <serpentTools.objects.containers.HomogUniv at 0x2220c78b048>,
 (30, 1.0, 2): <serpentTools.objects.containers.HomogUniv at 0x2220c78bb70>,
 (30, 10.0, 3): <serpentTools.objects.containers.HomogUniv at 0x2220c7917f0>,
 (40, 0.0, 1): <serpentTools.objects.containers.HomogUniv at 0x2220c78b1d0>,
 (40, 1.0, 2): <serpentTools.objects.containers.HomogUniv at 0x2220c78bdd8>,
 (40, 10.0, 3): <serpentTools.objects.containers.HomogUniv at 0x2220c791a58>}
```

The keys here are vectors indicating the universe ID, burnup [MWd/kgU], and burnup index corresponding to the point in the burnup schedule. These universes can be obtained by indexing this dictionary, or by using the <code>getUniv()</code> method

```
>>> univ0 = b0.universes[0, 1, 2]
>>> print(univ0)
>>> print(univ0.name)
>>> print(univ0.bu)
>>> print(univ0.step)
>>> print(univ0.day)
<HomogUniv from demo.coe>
0
1.0
2
0
>>> univ1 = b0.getUniv(0, burnup=1)
```

(continues on next page)

(continued from previous page)

```
>>> univ2 = b0.getUniv(0, index=2)
>>> assert univ0 is univ1 is univ2
```

Since the coefficient files do not store the day value of burnup, all <code>HomogUniv</code> objects created by the <code>BranchContainer</code> default to day zero.

Group constant data is stored in five dictionaries:

- 1. infExp: Expected values for infinite medium group constants
- 2. infunc: Relative uncertainties for infinite medium group constants
- 3. b1Exp: Expected values for leakge-corrected group constants
- 4. blunc: Relative uncertainties for leakge-corrected group constants
- 5. metaData: items that do not fit the in the above categories

```
>>> univ0.infExp
{'infDiffcoef': array([ 1.83961 ,  0.682022]),
'infFiss': array([ 0.00271604,  0.059773 ]),
'infRem': array([], dtype=float64),
'infSO': array([ 0.298689 , 0.00197521, 0.00284247, 0.470054 ]),
'infS1': array([ 0.0847372 , 0.00047366, 0.00062865, 0.106232 ]),
'infTot': array([ 0.310842,  0.618286])}
>>> univ0.infUnc
{ }
>>> univ0.b1Exp
{'b1Diffcoef': array([ 1.79892 , 0.765665]),
'b1Fiss': array([ 0.00278366,  0.0597712 ]),
'b1Rem': array([], dtype=float64),
'b1S0': array([ 0.301766 , 0.0021261 , 0.00283866, 0.470114 ]),
'b1S1': array([ 0.0856397 , 0.00051071, 0.00062781, 0.106232 ]),
'b1Tot': array([ 0.314521,  0.618361])}
>>> univ0.metaData
```

Group constants and their associated uncertainties can be obtained using the get () method.

```
>>> univ0.get('infFiss')
array([ 0.00286484,  0.0577559 ])
>>> try:
>>> univ0.get('infS0', uncertainty=True)
>>> except KeyError as ke: # no uncertainties here
>>> print(str(ke))
'Variable infS0 absent from uncertainty dictionary'
```

2.2.2 Iteration

The branching reader has a *iterBranches()* method that works to yield branch names and their associated *BranchContainer* objects. This can be used to efficiently iterate over all the branches presented in the file.

```
>>> for names, branch in r0.iterBranches():
>>> print(names, branch)
('nom', 'nom') <BranchContainer for nom, nom from demo.coe>
('B750', 'nom') <BranchContainer for B750, nom from demo.coe>
('B1000', 'nom') <BranchContainer for B1000, nom from demo.coe>
```

(continues on next page)

(continued from previous page)

```
('nom', 'FT1200') <BranchContainer for nom, FT1200 from demo.coe>
('B750', 'FT1200') <BranchContainer for B750, FT1200 from demo.coe>
('B1000', 'FT1200') <BranchContainer for B1000, FT1200 from demo.coe>
('nom', 'FT600') <BranchContainer for nom, FT600 from demo.coe>
('B750', 'FT600') <BranchContainer for B750, FT600 from demo.coe>
('B1000', 'FT600') <BranchContainer for B1000, FT600 from demo.coe>
```

2.2.3 User Control

The SERPENT set coefpara card already restricts the data present in the coeffient file to user control, and the *BranchingReader* includes similar control. Below are the various settings that the *BranchingReader* uses to read and process coefficient files.

```
>>> import six
>>> from serpentTools.settings import rc
>>> from serpentTools.settings import rc, defaultSettings
>>> for setting in defaultSettings:
>>>
       if 'xs' in setting or 'branching' in setting:
>>>
            print (setting)
>>>
            for k, v in six.iteritems(defaultSettings[setting]):
                print('\t', k+':', v)
branching.areUncsPresent
    default: False
    type: <class 'bool'>
    description: True if the values in the .coe file contain uncertainties
branching.intVariables
    default: []
    description: Name of state data variables to convert to integers for
    each branch
    type: <class 'list'>
branching.floatVariables
    default: []
    description: Names of state data variables to convert to floats for
    each branch
    type: <class 'list'>
xs.getInfXS
    default: True
    description: If true, store the infinite medium cross sections.
    type: <class 'bool'>
xs.getB1XS
    default: True
    description: If true, store the critical leakage cross sections.
    type: <class 'bool'>
xs.variableGroups
    default: []
    description: Name of variable groups from variables.yaml to be expanded
     into SERPENT variable to be stored
    type: <class 'list'>
xs.variableExtras
    default: []
    description: Full SERPENT name of variables to be read
    type: <class 'list'>
```

In our example above, the BOR and TFU variables represented boron concentration and fuel temperature, and can easily be cast into numeric values using the branching.intVariables and brancing.floatVariables

settings. From the previous example, we see that the default action is to store all state data variables as strings.

```
>>> assert isinstance(b0.stateData['BOR'], str)
```

As demonstrated in the *Group Constant Variables* example, use of xs.variableGroups and xs.variableExtras controls what data is stored on the *HomogUniv* objects. By default, all variables present in the coefficient file are stored.

```
>>> rc['branching.floatVariables'] = ['BOR']
>>> rc['branching.intVariables'] = ['TFU']
>>> rc['xs.getB1XS'] = False
>>> rc['xs.variableExtras'] = ['INF_TOT', 'INF_SCATTO']
>>> r1 = serpentTools.read(branchFile)
     : serpentTools: Inferred reader for demo.coe: BranchingReader
     : serpentTools: Preparing to read demo.coe
       : serpentTools: Done reading branching file
>>> b1 = r1.branches['B1000', 'FT600']
>>> b1.stateData
{'BOR': 1000.0,
 'DATE': '17/10/18',
 'TFU': 600,
'TIME': '10:26:48',
'VERSION': '2.1.29'}
>>> assert isinstance(b1.stateData['BOR'], float)
>>> assert isinstance(b1.stateData['TFU'], int)
```

Inspecting the data stored on the homogenized universes reveals only the variables explicitly requested are present

```
>>> univ4 = b1.getUniv(0, 0)
>>> univ4.infExp
{'infTot': array([ 0.313338,  0.54515 ])}
>>> univ4.b1Exp
{}
```

2.2.4 Conclusion

The *BranchingReader* is capable of reading coefficient files created by the SERPENT automated branching process. The data is stored according to the branch parameters, universe information, and burnup. This reader also supports user control of the processing by selecting what state parameters should be converted from strings to numeric types, and further down-selection of data.

2.3 DetectorReader

2.3.1 Basic Operation

The <code>DetectorReader</code> is capable of reading SERPENT detector files. These detectors can be defined with many binning parameters, listed on the SERPENT Wiki. One could define a detector that has a spatial mesh, <code>dx/dy/dz/</code>, but also includes reaction and material bins, <code>dr</code>, <code>dm</code>. Detectors are stored on the reader object in the <code>detectors</code> dictionary as custom <code>Detector</code> objects. Here, all energy and spatial grid data are stored, including other binning information such as reaction, universe, and lattice bins.

```
>>> from matplotlib import pyplot
>>> import serpentTools
       : serpentTools: Using version 0.2.1
>>> pinFile = 'fuelPin_det0.m'
>>> bwrFile = 'bwr_det0.m'
>>> pin = serpentTools.read(pinFile)
>>> bwr = serpentTools.read(bwrFile)
     : serpentTools: Inferred reader for fuelPin_det0.m: DetectorReader
       : serpentTools: Preparing to read fuelPin_det0.m
INFO
     : serpentTools: Done
TNFO
INFO
       : serpentTools: Inferred reader for bwr_det0.m: DetectorReader
INFO
       : serpentTools: Preparing to read bwr_det0.m
       : serpentTools: Done
>>> print(pin.detectors)
>>> print (bwr.detectors)
{'nodeFlx':
    <serpentTools.objects.containers.Detector object at 0x7fb3ae1db978>}
{ 'spectrum':
    <serpentTools.objects.containers.Detector object at 0x7fb3ae1db9e8>,
     <serpentTools.objects.containers.Detector object at 0x7fb3ae1dba20>}
```

These detectors were defined for a single fuel pin with 16 axial layers and a separate BWR assembly, with a description of the detectors provided in below:

Name	Description
nodeFlx	One-group flux tallied in each axial layer
spectrum	CSEWG 239 group stucture for flux and U-235 fission cross section
xymesh	Two-group flux for a 20x20 xy grid

For each Detector object, the full tally matrix is stored in the bins array.

```
>>> nodeFlx = pin.detectors['nodeFlx']
>>> print (nodeFlx.bins.shape)
(16, 12)
>>> nodeFlx.bins[:5, :]
array([[ 1.00000000e+00, 1.00000000e+00, 1.00000000e+00,
         1.00000000e+00,
                         1.00000000e+00,
                                           1.00000000e+00,
                        1.00000000e+00,
         1.00000000e+00,
                                           1.00000000e+00,
                                         4.53000000e-03],
         1.00000000e+00, 2.34759000e-02,
      [ 2.00000000e+00, 1.0000000e+00, 2.0000000e+00,
         1.00000000e+00, 1.0000000e+00, 1.00000000e+00,
         1.00000000e+00, 1.0000000e+00, 1.0000000e+00,
         1.00000000e+00, 5.75300000e-02, 3.38000000e-03],
      [ 3.00000000e+00, 1.00000000e+00, 3.00000000e+00,
         1.00000000e+00, 1.0000000e+00, 1.0000000e+00,
         1.00000000e+00, 1.00000000e+00, 1.00000000e+00,
         1.00000000e+00, 8.47000000e-02, 2.95000000e-03],
                         1.00000000e+00, 4.0000000e+00,
      [ 4.00000000e+00,
         1.00000000e+00,
                         1.00000000e+00,
                                           1.00000000e+00,
                         1.00000000e+00,
         1.00000000e+00,
                                           1.00000000e+00,
         1.00000000e+00,
                          1.02034000e-01,
                                           2.63000000e-031,
        5.00000000e+00,
                          1.00000000e+00,
                                           5.00000000e+00,
                        1.00000000e+00,
         1.00000000e+00,
                                           1.00000000e+00,
                                         1.00000000e+00,
         1.00000000e+00,
                        1.00000000e+00,
                                           2.31000000e-03]])
         1.00000000e+00,
                         1.10384000e-01,
```

2.3. DetectorReader 11

Here, only three columns are changing:

- column 0: universe column
- column 10: tally column
- column 11: errors

Note: For SERPENT-1, there would be an additional column 12 that contained the scores for each bin

Once each detector is given this binned tally data, the reshape() method is called to recast the tallies, errors, and, if applicable, the scores columns into individual, multidimensional arrays. For this case, since the only variable bin quantity is that of the universe, these will all be 1D arrays.

Bin information is retained through the indexes attribute. This is an *OrderedDictionary*, as the keys are placed according to their column position. These postions can be found in the SERPENT Manual, and are provided in the DET COLS tuple

Each item in the indexes ordered dictionary corresponds to the unique values of that bin in the original bins array. Here, universe is the first item and contains an equal number of elements to the size of the first (and only) axis in the nodeFlx tally matrix

```
>>> assert nodeFlx.indexes['universe'].size == nodeFlx.tallies.size
```


2.3.2 Plotting Routines

Each Detector object is capable of simple 1D and 2D plotting routines. The simplest 1D plot method is simply plot (), however a wide range of plot options are supported.

Option	Description
what	What data to plot
ax	Pre-prepared figure on which to add this plot
xdim	Quantity from indexes to use as x-axis
sigma	Confidence interval to place on errors
steps	Draw tally values as constant inside bin


The plot routine also accepts various options, which can be found in the matplotlib.pyplot.plot documentation

```
>>> nodeFlx.plot()
```




```
>>> ax = nodeFlx.plot(steps=True, label='steps')
>>> nodeFlx.plot(sigma=100, ax=ax, marker='x', label='sigma')
>>> ax.legend()
```

2.3. DetectorReader



Passing what='errors' to the plot method plots the associated relative errors, rather than the tally data on the y-axis. Similarly, passing a key from indexes as the xdim argument sets the x-axis to be that specific index.





For detectors that include some grid matrices, such as spatial or energy meshes DET<name>E, these arrays are stored in the grids dictionary

```
>>> spectrum = bwr.detectors['spectrum'] (continues on next page)
```

(continued from previous page)


```
print(spectrum.grids['E'][:5, :])
] ]
    1.00002000e-11
                      4.13994000e-07
                                        2.07002000e-071
    4.13994000e-07
                      5.31579000e-07
                                        4.72786000e-071
    5.31579000e-07
                      6.25062000e-07
                                        5.78320000e-07]
    6.25062000e-07
                                        6.53811000e-07]
                      6.82560000e-07
    6.82560000e-07
                      8.33681000e-07
                                        7.58121000e-07]]
```

The spectrumPlot() method is designed to prepare plots of energy spectra. Supported keyword arguments method include

Option	Default	Description
normalize	True	Normalize tallies per unit lethargy
sigma	3	Level of confidence for statistical errors
xscale	'log'	Set the x scale to be log or linear
yscale	'linear'	Set the y scale to be log or linear

Since our detector has energy bins and reaction bins, we need to reduce down to one-dimension with the fixed command. More on this in the next section. Here, the spectrum is plotted for the first reaction type, total flux for this detector.

```
>>> spectrum.spectrumPlot(fixed={'reaction': 1})
```



2.3.3 Multi-dimensional Detectors

The <code>Detector</code> objects are capable of reshaping the detector data into an array where each axis corresponds to a varying bin. In the above examples, the reshaped data was one-dimensional, because the detectors only tallied data against one bin, universe and energy. In the following example, the detector has been configured to tally the fission and capture rates (two <code>dr</code> arguments) in an XY mesh.

2.3. DetectorReader 15

```
>>> xy = bwr.detectors['xymesh']
>>> for key in xy.indexes:
>>> print(key, xy.indexes[key])
energy [1 2]
ymesh [1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20]
xmesh [1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20]
```

Traversing the first axis in the tallies array corresponds to changing the value of the reaction. The second axis corresponds to changing ymesh values, and the final axis reflects changes in xmesh.

```
>>> print(xy.bins.shape)
(800, 12)
>>> print(xy.tallies.shape)
(2, 20, 20)
>>> print(xy.bins[:5, 10])
[ 0.0401505  0.0352695  0.0330053  0.0292071  0.0267413]
>>> print(xy.tallies[0, 0, :5])
[ 0.0401505  0.0352695  0.0330053  0.0292071  0.0267413]
```

Slicing

As the detectors produced by SERPENT can contain multiple bin types, as seen in DET_COLS, obtaining data from the tally data can become complicated. This retrieval can be simplified using the slice() method. This method takes an argument indicating what bins (keys in indexes) to fix at what position.

If we want to retrive the tally data for the fission reaction in the spectrum detector, you would instruct the slice() method to use column 2 along the axis that corresponds to the reaction bin

```
>>> print(spectrum.indexes['reaction'])
[1 2]
>>> spectrum.slice({'reaction': 2})[:20]
array([ 1.84253000e+03,  3.27275000e+01,  1.65728000e+01,  7.78628000e+00,  1.56444000e+01,  3.88358000e+00,  2.43967000e+01,  1.42860000e+01,  5.06925000e+00,  5.08734000e+00,  4.62725000e+00,  1.03671000e+01,  1.76183000e+00,  7.40425000e+00,  3.71261000e+00,  3.10994000e+01,  1.45352000e+01,  1.13481000e+01,  1.80058000e+01,  1.57873000e+01])
```

As the fission reaction corresponded to reaction tally 1 in the original matrix.

This method also works for slicing the error and score matrices by using what='errors' or 'scores', respectively.


This call returns the relative error in the fission rate, reaction 2.

Plotting

For data with dimensionality greater than one, the meshPlot() method can be used to plot some 2D slice of the data. Passing a dictionary as the fixed argument restricts the tally data down to two dimensions. Since the xymesh

detector is three dimensions, (energy, x, and y), we must pick an energy group to plot.


```
>>> xy.meshPlot('x', 'y', fixed={'energy': 1});
# plot the fast spectrum flux
```




The meshPlot () also supports a range of labeling options

```
>>> spectrum.meshPlot('e', 'reaction', what='errors',
... ylabel='Reaction type',
... xlabel='Energy [MeV]');
```

2.3. DetectorReader




Using the slicing arguments allows access to the 1D plot methods from before



The underlying matplotlib plot routines can be used to plot multiple data sets on the same plot.

```
>>> ax = pyplot.axes()
>>> labels = (
... 'flux',
... r'$\sigma_f^{(u235)\psi$') # render as mathtype
>>> reactions = spectrum.indexes['reaction']
>>> for reac, label in zip(reactions, labels):
... spectrum.spectrumPlot({'reaction': reac}, steps=True, sigma=3,
... ax=ax, label=label)
>>> ax.set_ylabel('Normalized tally per unit lethargy')
>>> ax.legend()
```



2.3.4 Conclusion

The <code>DetectorReader</code> is capable of reading and storing detector data from SERPENT detector files. The data is stored on custom <code>Detector</code> objects, capable of reshaping tally and error matrices into arrays with dimensionality reflecting the detector binning. These <code>Detector</code> objects have simple methods for retrieving and plotting detector data.

2.3.5 References

1. J. Leppänen, M. Pusa, T. Viitanen, V. Valtavirta, and T. Kaltiaisenaho. "The Serpent Monte Carlo code: Status, development and applications in 2013." Ann. Nucl. Energy, 82 (2015) 142-150

2.3. DetectorReader

2.4 DepletionReader

2.4.1 Basic Operation

SERPENT produces a burned material file, containing the evolution of material properties through burnup for all burned materials present in the problem. The <code>DepletionReader</code> is capable of reading this file, and storing the data inside <code>DepletedMaterial</code> objects. Each such object has methods and attributes that should ease analysis.

```
>>> import six
>>> import serpentTools
>>> from serpentTools.settings import rc
INFO : serpentTools: Using version 0.2.1
>>> depFile = 'demo_dep.m'
>>> dep = serpentTools.read(depFile)
INFO : serpentTools: Inferred reader for demo_dep.m: DepletionReader
INFO : serpentTools: Preparing to read demo_dep.m
INFO : serpentTools: Done reading depletion file
```

The materials read in from the file are stored in the materials dictionary, where the keys represent the name of specific materials, and the corresponding values are the depleted material.

```
>>> dep.materials
{'bglass0': <serpentTools.objects.materials.DepletedMaterial at 0x23905154668>,
  'fuel0': <serpentTools.objects.materials.DepletedMaterial at 0x2390578eeb8>,
  'total': <serpentTools.objects.materials.DepletedMaterial at 0x2390579e978>}
```

Metadata, such as the isotopic vector and depletion schedule are also present inside the reader

2.4.2 DepletedMaterial

As mentioned before, all the material data is stored inside these <code>DepletedMaterial</code> objects. These objects share access to the metadata of the reader as well.

```
>>> fuel = dep.materials['fuel0']
>>> fuel.burnup
array([ 0. , 0.02, 0.04, ..., 1.36, 1.38, 1.4 , 1.42])
>>> fuel.days is dep.metadata['days']
True
```

All of the variables present in the depletion file for this material are present, stored in the data dictionary. A few properties commonly used are accessible as attributes as well.

```
>>> fuel.data.keys()
dict_keys(['a', 'adens', 'burnup', 'gsrc', ..., 'volume'])
>>> fuel.adens
array([[ 0.00000000e+00,  2.43591000e-09,  4.03796000e-09, ...,
```

(continues on next page)

(continued from previous page)

```
4.70133000e-09, 4.70023000e-09, 4.88855000e-09],
[ 0.00000000e+00, 6.06880000e-09, 8.11783000e-09, ...,
  8.05991000e-09, 8.96359000e-09,
                                  9.28554000e-09],
[ 4.48538000e-06,
                  4.48486000e-06,
                                  4.48432000e-06, ...,
                                    4.44611000e-06],
  4.44726000e-06,
                  4.44668000e-06,
[ 0.00000000e+00,
                   3.03589000e-11,
                                    7.38022000e-11, ...,
  1.62829000e-09,
                   1.63566000e-09,
                                    1.64477000e-09],
[ 0.00000000e+00, 1.15541000e-14, 2.38378000e-14, ...,
  8.60736000e-13, 8.73669000e-13, 8.86782000e-13],
[ 6.88332000e-02, 6.88334000e-02, 6.88336000e-02, ...,
  6.88455000e-02, 6.88457000e-02, 6.88459000e-02]])
```

Similar to the original file, the rows of the matrix correspond to positions in the isotopic vector, and the columns correspond to positions in burnup/day vectors.

```
>>> fuel.mdens.shape # rows, columns
(34, 72)
>>> fuel.burnup.shape
(72,)
>>> len(fuel.names)
34
```

2.4.3 Data Retrieval

At the heart of the <code>DepletedMaterial</code> is the <code>getValues()</code> method. This method acts as an slicing mechanism that returns data for a select number of isotopes at select points in time.

```
>>> dayPoints = [0, 5, 10, 30]

>>> iso = ['Xe135', 'U235']

>>> vals = fuel.getValues('days', 'a', dayPoints, iso)

>>> print(vals.shape)

(2, 4)


>>> print(vals)

[[ 0.00000000e+00     3.28067000e+14     3.24606000e+14     3.27144000e+14]

[ 5.36447000e+07     5.34519000e+07     5.32499000e+07     5.24766000e+07]]
```

The DepletedMaterial uses this slicing for the built-in plot () method

```
>>> fuel.plot('days', 'ingTox', dayPoints, iso, ylabel='Ingenstion Toxicity');
```



2.4.4 Limitations

Currently, the DepletionReader cannot catch materials with underscore in the name, due to variables like ING_TOX also containing an underscore. Issue #58

2.4.5 Settings

The DepletionReader also has a collection of settings to control what data is stored. If none of these settings are modified, the default is to store all the data from the output file.

```
>>> from serpentTools.settings import rc, defaultSettings
   for setting in defaultSettings:
        if 'depletion' in setting:
>>>
>>>
            print(setting)
>>>
            for k, v in six.iteritems(defaultSettings[setting]):
>>>
                print('\t', k, v)
depletion.materials
     type <class 'list'>
     description Names of materials to store. Empty list -> all materials.
     default []
depletion.processTotal
    type <class 'bool'>
    description Option to store the depletion data from the TOT block
    default True
depletion.materialVariables
    type <class 'list'>
    description Names of variables to store. Empty list -> all variables.
    default []
depletion.metadataKeys
```

(continues on next page)

(continued from previous page)

```
type <class 'list'>
description Non-material data to store, i.e. zai, isotope names, burnup schedule,

options default
default ['ZAI', 'NAMES', 'DAYS', 'BU']
```

Below is an example of configuring a DepletionReader that only stores the burnup days, and atomic density for all materials that begin with bqlass followed by at least one integer.

Note: Creating the DepletionReader in this manner is functionally equivalent to serpentTools. read(depFile)

```
>>> rc['depletion.processTotal'] = False
>>> rc['depletion.metadataKeys'] = ['BU']
>>> rc['depletion.materialVariables'] = ['ADENS']
>>> rc['depletion.materials'] = [r'bglass\d+']
>>> bgReader = serpentTools.parsers.DepletionReader(depFile)
>>> bgReader.read()
       : serpentTools: Preparing to read demo_dep.m
        : serpentTools: Done reading depletion file
>>> bgReader.materials
{'bglass0': <serpentTools.objects.materials.DepletedMaterial at 0x239057dcb00>}
>>> bglass = bgReader.materials['bglass0']
>>> bglass.data
{'adens': array([[ 0.
                            , 0. , 0.
                                                             \cap
                                                                         \cap
          0.
                   ],
                     0.
        [ 0.
                               , 0.
                                                    0.
                                                                0.
          0.
                   ],
                     0.
        [ 0.
                                  0.
                                                                0.
                                            , ...,
          0.
                   1,
        . . . ,
                     0.
        [ 0.
                                  0.
                                                    0.
                                                                0.
                                            , ...,
          0.
                   ],
                      0.
        [ 0.
                               , 0.
                                            , ...,
                                                    0.
                                                                0.
                   ],
        [0.0715841, 0.0715843, 0.0715845, ..., 0.0715968, 0.0715969,
          0.0715971]])}
>>> bglass.data.keys()
dict_keys(['adens'])
```

2.4.6 Conclusion

The DepletionReader is capable of reading and storing all the data from the SERPENT burned materials file. Upon reading, the reader creates custom DepletedMaterial objects that are responsible for storing and retrieving the data. These objects also have a handy plot method for quick analysis. Use of the rc settings control object allows increased control over the data selected from the output file.

2.4.7 References

1. J. Leppänen, M. Pusa, T. Viitanen, V. Valtavirta, and T. Kaltiaisenaho. "The Serpent Monte Carlo code: Status, development and applications in 2013." Ann. Nucl. Energy, 82 (2015) 142-150

THREE

API

3.1 Settings

class serpentTools.settings.UserSettingsLoader Bases: dict

Class that stores the active user settings.

expandVariables()

Extend the keyword groups into lists of serpent variables.

Returns Names of all variables to be scraped

Return type set

getReaderSettings (settingsPreffix)

Get all module-wide and reader-specific settings.

Parameters settingsPreffix $(str\ or\ list)$ - Name of the specific reader. Will look for settings that lead with readerName, e.g. depletion.metadataKeys or xs. variables

Returns Single level dictionary with settingName: settingValue pairs

Return type dict

Raises KeyError – If the reader name is not located in the readers settings dictionary

loadYaml (filePath, strict=True)

Update the settings based on the contents of the yaml file

New in version 0.2.0.

Parameters

- filePath (str, or FileType) Path to config file
- **strict** (bool) Fail at the first incorrect setting. If false, failed settings will not be loaded and alerts will be raised

Raises

- KeyError or TypeError If settings found in the config file are not valid
- FileNotFound or OSError If the file does not exist

setValue (name, value)

Set the value of a specific setting.

Parameters

- name (str) Full name of the setting
- value (value to be set) -

Raises

- KeyError If the value is not one of the allowable options or if the setting does not match an existing setting
- TypeError If the value is not of the correct type

3.2 Messages

System-wide methods for producing status update and errors.

See also:

- https://docs.python.org/2/library/logging.html
- https://www.python.org/dev/peps/pep-0391/

```
\textbf{exception} \ \texttt{serpentTools.messages.} \textbf{MismatchedContainersError}
```

Bases: serpentTools.messages.SamplerError

Attempting to sample from dissimilar containers

```
exception serpentTools.messages.SamplerError
```

Bases: serpentTools.messages.SerpentToolsException

Base-class for errors in sampling process

exception serpentTools.messages.SerpentToolsException

Bases: Exception

Base-class for all exceptions in this project

serpentTools.messages.critical(message)

Log that something has gone horribly wrong.

serpentTools.messages.debug(message)

Log a debug message.

serpentTools.messages.deprecated(useInstead)

Decorator that warns that different function should be used instead.

serpentTools.messages.error(message)

Log that something caused an exception but was suppressed.

serpentTools.messages.info(message)

Log an info message, e.g. status update.

 ${\tt serpentTools.messages.updateLevel}\ (level)$

Set the level of the logger.

serpentTools.messages.warning(message)

Log a warning that something could go wrong or should be avoided.

serpentTools.messages.willChange(changeMsg)

Decorator that warns that some functionality may change.

26 Chapter 3. API

3.3 Parser Module

The main module associated with reading SERPENT files. For information on each individual reader, please see the dedicated file listed below

Reader	Hyperlink
Branching	Branching Reader
Bumat	Bumat Reader
Depletion	Depletion Reader
Detector	Detector Reader
FissionMatrix	Fission Matrix Reader
Results	Results Reader

serpentTools.parsers.inferReader(filePath)

Attempt to infer the correct reader type.

Parameters filePath (str) – File to be read.

Raises SerpentToolsException - If a reader cannot be inferred

serpentTools.parsers.read(filePath, reader='infer')

Simple entry point to read a file and obtain the processed reader.

Note: If you know the type of reader you will be using, it is best to either pass in the string argument, or directly use the appropriate reader class

Parameters

- **filePath** (str) Path to the file to be reader
- **reader** (str or callable) Type of reader to use. If a string is given, then the actions described below will happen. If callable, then that function will be used with the file path as the first argument.

String argument	Action
infer	Infer the correct reader based on the file
dep	DepletionReader
branch	BranchingReader
det	DetectorReader
results	ResultsReader
bumat	BumatReader
fission	FissionMatrixReader

Returns Correct subclass corresponding to the file type

Return type serpentTools.objects.readers.BaseReader

Raises

- AttributeError If the object created by the reader through reader (filePath) does not have a read method.
- SerpentToolsException If the reader could not be inferred or if the requested reader string is not supported

3.3. Parser Module 27

NotImplementedError - This has the ability to load in readers that may not be complete, and thus the read method may raise this error.

serpentTools.parsers.depmtx(fileP)

Read the contents of the depmtx file and return contents

Note: If scipy is not installed, matrix A will be full. This can cause some warnings or errors if sparse or non-sparse solvers are used.

Parameters fileP (str) – Path to depletion matrix file

Returns

- **t** (*float*) Length of time
- **n0** (*numpy.ndarray*) Initial isotopic vector
- zai (numpy.array) String identifiers for each isotope in n0 and n1
- a (numpy.array or scipy.sparse.csc_matrix) Decay matrix. Will be sparse if scipy is installed
- n1 (numpy.array) Final isotopic vector

3.4 Parsing Engines

The classes contained in serpentTools/engines.py are part of the drewtils v0.1.9 package and are provided under the following license:

The MIT License (MIT)

Copyright (c) Andrew Johnson, 2017

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

These are designed to facilitate the parsing of files with a regular structure. For example, the depletion files all contain "chunks" of data that are separated by empty lines. Each chunk leads off with either the name of the material and associated variable, or the metadata, e.g. ZAI, DAYS. These parsers help break up these files into more digestible pieces.

Note: For developers, it is not required that these classes be used. These are bundled with this project to eliminate the need to install extra packages. Some of the readers, like the *BranchingReader* are not well suited for this type

28 Chapter 3. API

```
of parsing.
```

```
class serpentTools.engines.KeywordParser(filePath, keys, separators=None, eof=")
     Bases: serpentTools.engines._TextProcessor
     Class for parsing a file for chunks separated by various keywords.
          Parameters
                • filePath (str) – Object to be read. Any object with read and close methods
                • keys (Iterable) – List of keywords/phrases that will indicate the start of a chunk
                • separators (Iterable or None) - List of additional phrases that can separate two
                  chunks. If not given, will default to empty line '\n'.
                • eof (str) – String to indicate the end of the file
     line
          str - Most recently read line
     parse()
          Parse the file and return a list of keyword blocks.
              Returns List of key word argument chunks.
              Return type list
     yieldChunks()
          Return each chunk of text as a generator.
              Yields list – The next chunk in the file.
class serpentTools.engines.PatternReader(filePath)
     Bases: serpentTools.engines._TextProcessor
     Class that can read over a file looking for patterns.
          Parameters filePath (str) – path to the file that is to be read
     line
          str - Most recently read line
     match
          regular expression match or None – Match from the most recently read line
     searchFor (pattern)
          Return true if the pattern is found.
              Parameters pattern (str or compiled regular expression) -
              Returns bool
              Return type True if the pattern was found
     yieldMatches (pattern)
          Generator that returns all match groups that match pattern.
              Parameters pattern(str or compiled regular expression) - Seek through the
                  file and yield all match groups for lines that contain this patten.
              Yields sequential match groups
```

3.5 Containers

Many of the readers utilize custom built objects for storing data in a logical and accessible format. These containers are detailed here.

Note: Variables taken from SERPENT will be converted to mixedCase and stored under those names. for example, INF TOT would be stored as infTot

Bases: object

Class that stores data for a single branch.

The BranchingReader stores branch variables and branched group constant data inside these container objects. These are used in turn to create HomogUniv objects for storing group constant data.

Parameters

- filePath (str) Path to input file from which this container was connected
- branchID (int) Index for the run for this branch
- branchNames (tuple) Name of branches provided for this universe
- **stateData** (dict) key: value pairs for branch variables

stateData

dict – Name: value pairs for the variables defined on each branch card

universes

dict - Dictionary storing the homogenized universe objects. Keys are tuples of (universeID, burnup, burnIndex)

addUniverse (univID, burnup=0, burnIndex=0, burnDays=0)

Add a universe to this branch.

Data for the universes are produced at specific points in time. The additional arguments help track when the data for this universe were created.

Warning: This method will overwrite data for universes that already exist

Parameters

- univID (int or str) Identifier for this universe
- burnup (float or int) Value of burnup [MWd/kgU]
- burnIndex (int) Point in the depletion schedule
- burnDays (int or float) Point in time

Returns newUniv

Return type serpentTools.objects.containers.HomogUniv

getUniv(univID, burnup=None, index=None)

Return a specific universe given the ID and time of interest

If burnup and index are given, burnup is used to search

30 Chapter 3. API

Parameters

- univID (int) Unique ID for the desired universe
- burnup (float or int) Burnup [MWd/kgU] of the desired universe
- index (int) Point of interest in the burnup index

Returns univ – Requested Universe

Return type serpentTools.objects.containers.HomogUniv

Raises

- KeyError: If the requested universe could not be found
- SerpentToolsException: If neither burnup nor index are given

orderedUniv

Universe keys sorted by ID and by burnup

3.5.1 Materials

Base class for storing material data from a depleted material file

While adens, mdens, and burnup are accessible directly with material.adens, all variables read in from the file can be accessed through the data dictionary:

```
>>> assert material.adens is material.data['adens']
>>> assert material.adens is material['adens']
# The three methods are equivalent
```

Parameters

- name (str) Name of this material
- metadata (dict) Dictionary with file metadata

data

dict – dictionary that stores all variable data

zai

list – Isotopic ZZAAA identifiers, e.g. 93325

names

list – Names of isotopes, e.g. U235

days

numpy.ndarray – Vector of total, cumulative days of burnup for the run that created this material

burnup

numpy.ndarray - Vector of total, cumulative burnup [MWd/kgU] for this specific material

adens

numpy.ndarray - 2D array of atomic densities where where row j corresponds to isotope j and column i corresponds to time i

mdens

numpy.ndarray - 2D array of mass densities where where row j corresponds to isotope j and column i corresponds to time i

3.5. Containers 31

```
getValues (xUnits, yUnits, timePoints=None, names=None)
```

Return material variable data at specified time points and isotopes

If the quantity yUnits corresponds to a vector in the data dictionary, e.g. burnup or volume, and not something that varies by isotope, then names does not have to be given

Parameters

- xUnits (str) name of x value to obtain, e.g. 'days', 'burnup'
- yUnits (str) name of y value to return, e.g. 'adens', 'burnup'
- **timePoints** (*list or None*) If given, select the time points according to those specified here. Otherwise, select all points
- names (list or None) If given, return y values corresponding to these isotope names. Otherwise, return values for all isotopes.

Returns Array of values.

Return type numpy.array

Raises

- AttributeError If the names of the isotopes have not been obtained and specific isotopes have been requested
- KeyError If at least one of the days requested is not present

```
class serpentTools.objects.materials.DepletedMaterial(name, metadata)
    Bases: serpentTools.objects.materials.DepletedMaterialBase
```

Base class for storing material data from a depleted material file

While adens, mdens, and burnup are accessible directly with material.adens, all variables read in from the file can be accessed through the data dictionary:

```
>>> assert material.adens is material.data['adens']
>>> assert material.adens is material['adens']
# The three methods are equivalent
```

Parameters

- name (str) Name of this material
- metadata (dict) Dictionary with file metadata

data

dict – dictionary that stores all variable data

zai

list – Isotopic ZZAAA identifiers, e.g. 93325

names

list – Names of isotopes, e.g. U235

days

numpy.ndarray - Vector of total, cumulative days of burnup for the run that created this material

burnup

numpy.ndarray – Vector of total, cumulative burnup [MWd/kgU] for this specific material

32 Chapter 3. API

adens

numpy.ndarray – 2D array of atomic densities where where row j corresponds to isotope j and column i corresponds to time i

mdens

numpy.ndarray - 2D array of mass densities where where row j corresponds to isotope j and column i corresponds to time i

addData(variable, rawData)

Add data straight from the file onto a variable.

Parameters

- **variable** (str) Name of the variable directly from SERPENT
- rawData (list) List of strings corresponding to the raw data from the file

plot (xUnits, yUnits, timePoints=None, names=None, ax=None, autolabel=True, legend=True, xlabel=None, ylabel=None, **kwargs)

Plot some data as a function of time for some or all isotopes.

Note: kwargs will be passed to the plot for all isotopes. If c='r' is passed, to make a plot red, then data for all isotopes plotted will be red and potentially very confusing.

Parameters

- xUnits (str) name of x value to obtain, e.g. 'days', 'burnup'
- yUnits (str) name of y value to return, e.g. 'adens', 'burnup'
- timePoints (list or None) If given, select the time points according to those specified here. Otherwise, select all points
- names (list or None) If given, return y values corresponding to these isotope names. Otherwise, return values for all isotopes.
- ax (None or matplotlib.pyplot.axes) If given, add the data to this plot. Otherwise, create a new plot
- legend (bool) Automatically add the legend
- autolabel (bool) Automatically label the axis
- xlabel (None or str) If given, use this as the label for the x-axis. Otherwise, use xUnits
- ylabel (None or str) If given, use this as the label for the y-axis. Otherwise, use yUnits
- **kwargs** Optional keyword arguments to pass to matplotlib.pyplot.plot

Returns Axes corresponding to the figure that was plotted

Return type matplotlib.pyplot.axes

See also:

- getValues()
- matplotlib.pyplot.plot()

3.5. Containers 33

3.5.2 Detectors

```
class serpentTools.objects.containers.DetectorBase(name)
    Bases: serpentTools.objects.NamedObject
```

Base class for classes that store detector data

Parameters name (str) - Name of this detector

grids

dict – Dictionary with additional data describing energy grids or mesh points

tallies

None or numpy.array – Reshaped tally data to correspond to the bins used

errors

None or numpy.array – Reshaped relative error data corresponding to bins used

scores

None or numpy.array – Reshaped array of tally scores. SERPENT 1 only

indexes

None or OrderedDict - Collection of unique indexes for each requested bin

meshPlot (xdim, ydim, what='tallies', fixed=None, ax=None, cmap=None, addcbar=True, xla-bel=None, ylabel=None, xscale='linear', yscale='linear')
Plot tally data as a function of two mesh dimensions

Parameters

- xdim (str) Primary dimension will correspond to x-axis on plot
- ydim (str) Secondary dimension will correspond to y-axis on plot
- what ({ 'tallies', 'errors', 'scores'}) Color meshes from tally data, uncertainties, or scores
- fixed (None or dict) Dictionary controlling the reduction in data down to one dimension
- ax (axes or None) Axes on which to plot the data
- cmap (None or str) Colormap to apply to the figure. If None, use default colormap
- addcbar (bool) If True, add a colorbar to the figure
- xlabel (None or str) Label to apply to x-axis. If not given, defaults to xdim
- ylabel (None or str) Label to apply to y-axis. If not given, defaults to ydim
- xscale ({'log', 'linear'}) Scale to apply to x-axis
- yscale({'log', 'linear'}) Scale to apply to y-axis

Returns ax - Ax on which the data was plotted

Return type pyplot.Axes

Raises

- SerpentToolsException If data to be plotted, with or without constraints, is not
 1D
- KeyError If the data set by what not in the allowed selection

See also:

slice()

plot (xdim=None, what='tallies', sigma=None, fixed=None, ax=None, xlabel=None, ylabel=None,
 steps=False, **kwargs)
 Shortcut routine for plotting 1D data

Parameters

- xdim (None or str) If not None, use the array under this key in indexes as the x axis
- what ({ 'tallies', 'errors', 'scores'}) Primary data to plot
- **sigma** (*None or int*) If given, apply this level of confidence to absolute errors. If not given, then error bars will not be used
- fixed (None or dict) Dictionary controlling the reduction in data down to one dimension
- ax (axes or None) Axes on which to plot the data
- **xlabel** (*None or str*) If given, apply this label to the x-axis. If xdim is given and xlabel is None, then xdim will be applied to the x-axis
- ylabel (None or str) If given, label to apply to y-axis
- **steps** (bool) If true, plot the data as constant inside the respective bins. Sets drawstyle to be steps-post unless drawstyle given in kwargs
- **kwargs** (*dict*) additional arguments to pass to the plot () of errorbar() function.

Returns ax

Return type matplotlib.AxesSubplot

Raises SerpentToolsException: If the data is not constrained to 1D

See also:

- slice()
- spectrumPlot () better options for plotting energy spectra

```
slice (fixed, data='tallies')
```

Return a slice of the reshaped array where certain axes are fixed

Parameters

- data ({ 'tallies', 'errors', 'scores'}) Which data set to slice
- **fixed** (dict) dictionary to aid in the restriction on the multidimensional array. Keys correspond to the various grids present in indexes while the values are used to

Returns reduced – View into the respective data where certain dimensions have been removed

Return type numpy.array

Raises

- SerpentToolsException If the data has not been reshaped or is None [e.g. scores]
- KeyError If the data set to slice not in the allowed selection

Parameters

3.5. Containers 35

- fixed (None or dict) Dictionary controlling the reduction in data down to one dimension
- ax (pyplot.Axes or None) Ax on which to plot the data
- normalize (bool) Normalize quantities per unit lethargy
- xlabel (str or None) Label for x-axis. Defaults to 'Energy [MeV]'
- ylabel (str or None) Label for y axis
- steps (bool) Plot tally as constant inside bin
- xscale ({'log', 'linear'}) Scale to apply to x axis
- yscale ({'log', 'linear'}) Scale to apply to y axis
- **sigma** (*int*) Level of confidence to apply to errors. Use for no error bars
- kwargs Additional arguments to pass to plot command

Returns ax – Axes on which the data was plotted

Return type pyplot.Axes

Raises SerpentToolsException - if number of rows in data not equal to number of energy groups

See also:

slice()

class serpentTools.objects.containers.Detector(name)

Bases: serpentTools.objects.containers.DetectorBase

Class that stores detector data from a single detector file

Parameters

- name (str) Name of this detector
- Attributes -
- bins (numpy.ndarray) Tally data directly from SERPENT file
- grids (dict) Dictionary with additional data describing energy grids or mesh points
- tallies (None or numpy.array) Reshaped tally data to correspond to the bins used
- errors (None or numpy.array) Reshaped relative error data corresponding to bins used
- scores (None or numpy.array) Reshaped array of tally scores. SERPENT 1 only
- indexes (None or OrderedDict) Collection of unique indexes for each requested bin

addTallyData(bins)

Add tally data to this detector

reshape()

Reshape the tally data into a multidimensional array

This method reshapes the tally and uncertainty data into arrays where the array axes correspond to specific bin types. If a detector was set up to tally two group flux in a $5 \times 5 \times 5$ mesh, then the resulting tally data would be in a $50 \times 12/13$ matrix in the original detN.m file. The tally data and relative error would be rebroadcasted into $2 \times 5 \times 5$ arrays, and the indexing information is stored in self.indexes

```
Returns shape – Dimensionality of the resulting array
```

Return type list

Raises SerpentToolsException: - If the bin data has not been loaded

3.5.3 Homogenized Universes

```
class serpentTools.objects.containers.HomogUniv(name, bu, step, day)
    Bases: serpentTools.objects.NamedObject
```

Class for storing homogenized universe specifications and retrieving them

Parameters

```
• name (str) – name of the universe
```

```
• bu (float) – burnup value
```

name

str – name of the universe

bu

float - burnup value

step

float – temporal step

day

float - depletion day

infExp

dict – Expected values for infinite medium group constants

infUnc

dict - Relative uncertainties for infinite medium group constants

b1Exp

dict – Expected values for leakage corrected group constants

b1Unc

dict - Relative uncertainties for leakage-corrected group constants

metadata

dict – Other values that do not not conform to inf/b1 dictionaries

addData(variableName, variableValue, uncertainty=False)

Sets the value of the variable and, optionally, the associate s.d.

Warning: This method will overwrite data for variables that already exist

Parameters

- variableName (str) Variable Name
- variableValue Variable Value

3.5. Containers 37

• uncertainty (bool) – Set to True in order to retrieve the uncertainty associated to the expected values

Raises TypeError – If the uncertainty flag is not boolean

get (variableName, uncertainty=False)

Gets the value of the variable VariableName from the dictionaries

Parameters

- variableName (str) Variable Name
- uncertainty (bool) Boolean Variable- set to True in order to retrieve the uncertainty associated to the expected values

Returns

- x Variable Value
- dx Associated uncertainty

Raises

- TypeError If the uncertainty flag is not boolean
- KeyError If the variable requested is not stored on the object

3.6 Branching Reader

The BranchingReader is designed to read the files generated by the automated burnup sequence. The output format is described at the SERPENT Wiki.

The reader stores homogenized universe data for each universe at each point in time for each branch in <code>HomogUniv</code> objects.

```
class serpentTools.parsers.branching.BranchingReader (filePath)
    Bases: serpentTools.objects.readers.XSReader
```

Parser responsible for reading and working with automated branching files.

```
Parameters filePath (str) – path to the depletion file
```

```
iterBranches()
```

Iterate over branches yielding paired branch IDs and containers

3.7 Bumat Reader

Warning: This reader is not implemented yet. This merely serves as a placeholder

Parser responsible for reading and working with burned material files.

Parameters filePath (str) – path to the depletion file

3.8 Depletion Reader

Warning: Does not support depleted materials with underscores, i.e. fuel_1 will not be matched with the current methods

class serpentTools.parsers.depletion.DepletionReader(filePath)

Bases: serpentTools.objects.readers.MaterialReader

Parser responsible for reading and working with depletion files.

Parameters filePath (str) – path to the depletion file

materials

dict — Dictionary with material names as keys and the corresponding DepletedMaterial class for that material as values

metadata

dict – Dictionary with file-wide data names as keys and the corresponding data, e.g. 'zai': [list of zai numbers]

settings

dict – names and values of the settings used to control operations of this reader

3.9 Detector Reader

class serpentTools.parsers.detector.DetectorReader(filePath)

Bases: serpentTools.objects.readers.BaseReader

Parser responsible for reading and working with detector files.

Parameters filePath (str) – path to the depletion file

detectors

dict - Dictionary where key, value pairs correspond to detector names and their respective <code>DetectorObject</code>

3.10 Fission Matrix Reader

Warning: This reader is not implemented yet. This merely serves as a placeholder

Bases: serpentTools.objects.readers.BaseReader

Parser responsible for reading and working with fission matrix files.

Parameters filePath (str) – path to the depletion file

3.11 Results Reader

Warning: This reader is not implemented yet. This merely serves as a placeholder

Parser responsible for reading and working with result files.

Parameters filePath (str) – path to the depletion file

3.12 Samplers

A common practice in Monte Carlo analysis is repeat a single case with a variety of new random number seeds. Averaging the results from these runs reduces the impact of stochastic uncertainty and can give a better picture of the *true* behavior of a system. The *Welcome!* package supports reading multiple output files of a common type and obtaining average values and associated uncertainties, while retaining data structure and retrieval methods similar to the single file cases.

3.12.1 Detector Sampler

This sampler extends the Sampler class for reading detector files.

```
class serpentTools.samplers.detector.DetectorSampler (files)
    Bases: serpentTools.samplers.Sampler
```

Class responsible for reading multiple detector files

The following checks are performed to ensure that all detectors are of similar structure and content

- 1. Each parser must have the same detectors
- 2. The reshaped tally data must be of the same size for all detectors

These tests can be skipped by setting <sampler.skipPrecheck> to be False

Parameters files (str or iterable) - Single file or iterable (list) of files from which to read. Supports file globs, *det0.m expands to all files that end with det0.m

detectors

dict - Dictionary where key, value pairs correspond to detector names and their respective <code>DetectorObject</code>

files

set – Unordered set containing full paths of unique files read

settings

dict – Dictionary of sampler-wide settings

parsers

set – Unordered set of all parsers that were successful

map

dict - Dictionary where key, value pairs are files and their corresponding parsers

```
class serpentTools.samplers.detector.SampledDetector(name, numFiles)
```

Bases: serpentTools.samplers.SampledContainer, serpentTools.objects.containers.DetectorBase

Class to store aggregated detector data

Note: free() sets allTallies, allErrors, and allScores to None. If <sampler.freeAll> is True, then free will be called after all files have been read and processed.

Parameters

- name (str) Name of this detector
- numFiles (int) Number of files that have been/will be read

grids

dict – Dictionary with additional data describing energy grids or mesh points

tallies

None or numpy.array – Reshaped tally data to correspond to the bins used

errors

None or numpy.array – Reshaped relative error data corresponding to bins used

scores

None or numpy.array – Reshaped array of tally scores. SERPENT 1 only

indexes

None or OrderedDict - Collection of unique indexes for each requested bin

Plot the mean tally value against all sampled detector data.

Parameters

- xdim (str) Bin index to place on the x-axis
- fixed (None or dict) Dictionary controlling the reduction in data down to one dimension
- ax (axes or None) Axes on which to plot the data. Create a new plot if not given
- xlabel (None or str) Label to apply to x-axis. If not given, defaults to xdim
- ylabel (None or str) Label to apply to y-axis. If not given, defaults to "Tally Data"
- xscale ({'log', 'linear'}) Scale to apply to x-axis
- yscale ({'log', 'linear'}) Scale to apply to y-axis
- autolegend (bool) If true, apply a label to this plot.

Returns Axes on which this figure was drawn

Return type matplotlib.pyplot.axes

Raises

• SamplerError – If allTallies is None, indicating this object has been instructed to free up data from all sampled files

3.12. Samplers 41

• SerpentToolsException – If data to be plotted, after applying fixed, is not one dimensional

3.12.2 DepletionSampler

This sampler extends the Sampler class for reading depletion files.

```
class serpentTools.samplers.depletion.DepletionSampler (files)
    Bases: serpentTools.samplers.Sampler
```

Class that reads and stores data from multiple *dep.m files

The following checks are performed in order to ensure that depletion files are of similar form:

- 1. Keys of materials dictionary are consistent for all parsers
- 2. Metadata keys are consistent for all parsers
- 3. Isotope names and ZZAAA metadata are equal for all parsers

These tests can be skipped by setting <sampler.skipPrecheck> to be False

Parameters files (str or iterable) - Single file or iterable (list) of files from which to read. Supports file globs, *det0.m expands to all files that end with det0.m

materials

dict – Dictionary with material names as keys and the corresponding DepletedMaterial class for that material as values

metadata

dict – Dictionary with file-wide data names as keys and the corresponding data, e.g. 'zai': [list of zai numbers]

metadataUncs

dict – Dictionary containing uncertainties in file-wide metadata, such as burnup schedule

allMdata

dict – Dictionary where key, value pairs are name of metadata and metadata arrays for all runs. Arrays with be of one greater dimension, as the first index corresponds to the file index.

files

set – Unordered set containing full paths of unique files read

settings

dict – Dictionary of sampler-wide settings

parsers

set – Unordered set of all parsers that were successful

map

dict – Dictionary where key, value pairs are files and their corresponding parsers

iterMaterials()

Yields material names and objects

class serpentTools.samplers.depletion.SampledDepletedMaterial (N, name, meta-

Bases: serpentTools.samplers.SampledContainer, serpentTools.objects.
materials.DepletedMaterialBase

Class that stores data from a variety of depleted materials

While adens, mdens, and burnup are accessible directly with material.adens, all variables read in from the file can be accessed through the data dictionary:

```
>>> assert material.adens is material.data['adens']
>>> assert material.adens is material['adens']
# The three methods are equivalent
```

Note: free() sets allData to an empty dictionary If <sampler.freeAll> is True, then free will be called after all files have been read and processed.

Parameters

- N (int) Number of containers to expect
- name (str) Name of this material
- **metadata** (dict) File-wide metadata for this run. Should contain ZAI and names for all isotopes, days, and burnup schedule

data

dict - dictionary that stores all variable data

zai

list – Isotopic ZZAAA identifiers, e.g. 93325

names

list – Names of isotopes, e.g. U235

days

numpy.ndarray – Vector of total, cumulative days of burnup for the run that created this material

burnup

numpy.ndarray - Vector of total, cumulative burnup [MWd/kgU] for this specific material

adens

numpy.ndarray - 2D array of atomic densities where where row j corresponds to isotope j and column i corresponds to time i

mdens

numpy.ndarray - 2D array of mass densities where where row j corresponds to isotope j and column i corresponds to time i

uncertainties

dict - Uncertainties for all variables stored in data

allData

dict – Dictionary where key, value pairs correspond to names of variables stored on this object and arrays of data from all files. The dimensionality will be increased by one, as the first index corresponds to the order in which files were loaded

free()

Clear up data from all sampled parsers

plot (xUnits, yUnits, timePoints=None, names=None, ax=None, sigma=3, legend=True, xlabel=None,
 ylabel=None, **kwargs)

Plot the average of some data vs. time for some or all isotopes.

3.12. Samplers 43

Note: kwargs will be passed to the errorbar plot for all isotopes. If c='r' is passed, to make a plot red, then data for all isotopes plotted will be red and potentially very confusing.

Parameters

- **xUnits** (str) name of x value to obtain, e.g. 'days', 'burnup'
- yUnits (str) name of y value to return, e.g. 'adens', 'burnup'
- **timePoints** (*list or None*) If given, select the time points according to those specified here. Otherwise, select all points
- names (list or None) If given, return y values corresponding to these isotope names. Otherwise, return values for all isotopes.
- ax (None or matplotlib.pyplot.axes) If given, add the data to this plot. Otherwise, create a new plot
- **sigma** (*int*) Confidence interval for uncertainties
- **legend** (bool) Automatically add the legend
- xlabel (None or str) If given, use this as the label for the x-axis. Otherwise, use xUnits
- ylabel (None or str) If given, use this as the label for the y-axis. Otherwise, use yUnits
- **kwargs** Optional keyword arguments to pass to matplotlib.pyplot.errorbar

Returns Axes corresponding to the figure that was plotted

Return type matplotlib.pyplot.axes

See also:

- getValues()
- matplotlib.pyplot.errorbar()

spreadPlot (xUnits, yUnits, isotope, timePoints=None, ax=None, xLabel=None, yLabel=None, auto-label=True, autolegend=True)

Plot the mean quantity and data from all sampled files.

Parameters

- xUnits (str) name of x value to obtain, e.g. 'days', 'burnup'
- yUnits (str) name of y value to return, e.g. 'adens', 'burnup'
- isotope (str) Plot data for this isotope
- timePoints (list or None) If given, select the time points according to those specified here. Otherwise, select all points
- ax (None or matplotlib.pyplot.axes) If given, add the data to this plot.
- **xLabel** (None or str) If given, use this as the label for the x-axis. Otherwise, use xUnits
- yLabel (None or str) If given, use this as the label for the y-axis.
- autolabel (bool) Apply xLabel and yLabel directly to the figure

• autolegend (bool) - Add a legend to the figure

Returns Axes corresponding to the figure that was plotted

Return type matplotlib.pyplot.axes

Raises SamplerError – If self.allData is empty. Sampler was instructed to free all materials and does not retain data from all containers

See also:

plot()

3.12.3 Base Classes

```
class serpentTools.samplers.Sampler (files, parser)
```

Bases: object

Base class for reading multiple files of of a similar type

Parameters

- **files** (str or iterable) Single file or iterable (list) of files from which to read. Supports file globs, *det0.m expands to all files that end with det0.m
- parser (subclass of BaseReader) Class that will be used to read all files

files

set – Unordered set containing full paths of unique files read

settings

dict – Dictionary of sampler-wide settings

parsers

set – Unordered set of all parsers that were successful

map

dict – Dictionary where key, value pairs are files and their corresponding parsers

Raises serpentTools.messages.SamplerError - If parser is not a subclass of BaseReader

free()

Remove all parsers and individual containers from memory

process()

Process the repeated files to obtain true uncertainties

read()

Read all the files and create parser objects

```
class serpentTools.samplers.SampledContainer(N, expectedContainer)
    Bases: object
```

Base class for containers that produce averages and deviations from multiple files

Parameters

- N (int) Number of containers to expect
- expectedContainer (class) What class to expect for all incoming containers

finalize()

Produce final uncertainties from all aggregated runs

3.12. Samplers 45

loadFromContainer(container)

Copy data from a similar container.

Parameters container – Incoming container from which to take data.

Raises

- serpentTools.messages.MismatchedContainersError If the incoming container is not the expected type declared at construction
- serpent Tools.messages.SamplerError If more containers have been loaded than specified at construction

CHAPTER

FOUR

DEVELOPER'S GUIDE

This section serves as a guide for people who would like to add functionality to this project. If that is not your desire, this chapter can be skipped without any loss of comprehension.

4.1 Contributing

First, thanks for your interest in contributing to this project! This document should help us expedite the process of reviewing issues and pull requests. For a quick look at all the issues that are up for grabs, take a look at the current unclaimed issues. If you claim an issue, use the Assignees setting to let us know that you've got it!

4.1.1 Scope

The scope of this project is to simplify and expedite analysis stemming from SERPENT outputs. In the future we may expand this project to expand to interacting heavily with input files, but that is currently beyond the scope of this project. Any and all issues, features and pull requests will be examined through this scope.

4.1.2 Issues

The goal for this project is to become the de facto method for processing SERPENT outputs and, if you're looking at this, there is some way we can improve. The GitHub issue tracker is the preferred way to post bug reports and feature requests.

Bug Reports

The more information given, the quicker we can reproduce and hopefully resolve the issue. Please see issue-template for a template that should be used for reporting bugs. One of the developers will add a bug label and start moving to resolve the issue posthaste.

Feature Requests

We are very interested in adding functionality from the SERPENT community! Requests can be done through the issue tracker as well. You can create an issue on the issue tracker with [Feature] or [Request] in the title. Describe what you would like to add, some expected results, and the purpose behind the feature. The development team will apply an enhancement label and proceed accordingly.

4.1.3 Pull Requests

Pull requests are how we review, approve, and incorporate changes into the master branch. If you have code you want to contribute, please look at the content in the *Developer's Guide* for things like *Pull Request Checklist*, *Coding Style*, and more.

When your content is ready for the pull request, follow the pull-request-template and make a request! Someone of the core development team will review the changes according to the criteria above and make changes and/or approve for merging!

The develop branch is the primary branch for this project. All pull requests, except for bugs on public releases, should be compared against this branch. When a pull request is approved and has passed the required checks, it should be squashed and merged into the develop branch. Squashing a branch converts a series of commits into a single commit onto the main branch, creating a tidy git history.

For pull requests into master, as in releases, these should simply be merged without squashing. When viewing the git log on the master or develop branches, one is presented only with approved and closed pull requests, not incremental commits that led to a PR being closed.

4.2 Data Model

This project has two key offerings to the SERPENT community.

- 1. Scripting tools that are capable of interpreting the output files
- 2. Purpose-built containers for storing, accessing, and utilizing the data in the output files

4.2.1 Readers

The readers are the core of this package, and should have a logical and consistent method for structuring data. Each reader contained in this project should:

- 1. Be capable of reading the intended output file
- 2. Yield to the user the data in a logical manner
- 3. Default to storing all the data without user input
- 4. Receive input from the user regarding what data to restrict/include
- 5. Report activity at varying levels, including failure, to the user

The third and fourth points refer to use of the serpentTools.settings module to receive user input. The final point refers to use of the logging and messaging functions included in serpentTools.messages.

For example, the DepletionReader stores data in the following manner:

```
Reader
| - filePath
| - fileMetadata
| - isotope names
| - isotope ZAIs
| - depletion schedule in days and burnup
| - materials
# for each material:
| - DepletedMaterial-n
| - name
| - atomic density
```

(continues on next page)

(continued from previous page)

```
| - mass density
| - volume
| etc
```

Here, the reader primarily creates and stores material objects, and the useful data is stored on these objects. Some files, like the fission matrix and depletion matrix files may not have a structure that naturally favors this object-oriented approach.

4.2.2 Containers

The readers are primarily responsible for creating and populating containers, that are responsible for storing and retrieving data. Just like the <code>DepletedMaterial</code> has shortcuts for analysis like <code>getValues()</code> and <code>plot()</code>, each such container should easily and naturally provide access to the data, and also perform some common analysis on the data.

4.3 Coding Style

For the most part, this project follows the PEP 8 standard with a few differences. Some points are included here

- 79 characters per line
- · Four spaces per indentation level
- Avoiding extraneous whitespace:

```
Yes: spam(ham[1], {eggs: 2})
No: spam( ham[ 1 ], { eggs: 2 } )
```

Some of the specific style points for this project are included below

- · mixedCase for variables, methods, and functions
- CamelCase for classes:

```
class DemoClass(object):
    def doSomething(self, arg0, longerArgumentName):
        pass
```

• Directly call the __init__ method from a parent class, e.g.:

```
class MyQueue(list):

    def __init__(self, items):
        list.__init__(self)
        self.extend(items)
```

- Arrange imports in the following order:
 - 1. imports from the standard library: os, sys, etc.
 - 2. imports from third party code: numpy, matplotlib, etc.
 - 3. imports from the serpentTools package
- Longer import paths are preferred to shorter:

4.3. Coding Style 49

```
# yes
from really.long.path.to.a import function
function()
# not preferred
import really
really.long.path.to.a.function()
```

4.4 Documentation

All public functions, methods, and classes should have adequate documentation through docstrings, examples, or inclusion in the appropriate file in the docs directory. Good forethought into documenting the code helps resolve issues and, in the case of docstrings, helps produce a full manual.

4.4.1 Docstrings

Docstrings are defined in PEP 257 and are characterized by """triple double quotes""". These can be used to reduce the effort in creating a full manual, and can be viewed through python consoles to give the user insight into what is done, what is required, and what is returned from a particular object. This project uses numpy style docstrings, examples of which are given below

Functions and Methods

Below is the depmtx () function annotated using short and longer docstrings:

```
def depmtx(filePath):
    """Return t, no, zai, a, and n1 values from the depmtx file."""
```

or:

```
def depmtx(filePath):
   Read the contents of the ``depmtx`` file and return contents
    .. note::
       If ``scipy`` is not installed, matrix ``A`` will be full.
       This can cause some warnings or errors if sparse or
       non-sparse solvers are used.
   Parameters
   fileP: str
       Path to depletion matrix file
   Returns
   t: float
       Length of time
   n0: numpy.ndarray
       Initial isotopic vector
   zai: numpy.array
       String identifiers for each isotope in ``n0`` and ``n1``
```

(continues on next page)

(continued from previous page)

```
a: numpy.array or scipy.sparse.csc_matrix

Decay matrix. Will be sparse if scipy is installed

n1: numpy.array

Final isotopic vector

"""
```

Both docstrings indicate what the function does, and what is returned. The latter, while more verbose, is preferred in most cases, for the following reasons. First, far more information is yielded to the reader. Second, the types of the inputs and outputs are given and clear. Some IDEs can obtain the expected types from the docstrings and inform the user if they are using an incorrect type.

More content can be added to the docstring, including

- · Raises Errors/warnings raised by this object
- See Also follow up information that may be useful
- Yields If this object is a generator. Similar to Returns

Classes

Classes can have a more lengthy docstring, as they often include attributes to which the class has access. Below is an example of the docstring for the DepletionReader:

```
Parser responsible for reading and working with depletion files.

Parameters
--------
filePath: str
   path to the depletion file

Attributes
----------
materials: dict
   Dictionary with material names as keys and the corresponding
   :py:class:`~serpentTools.objects.DepletedMaterial` class
   for that material as values

metadata: dict
   Dictionary with file-wide data names as keys and the
   corresponding dataas values, e.g. 'zai': [list of zai numbers]

settings: dict
   names and values of the settings used to control operations
   of this reader
```

Class docstrings can be added to the class signature, or to the __init__ method, as:

```
class Demo(object):
    """
    Demonstration class

Parameters
-----
x: str
```

(continues on next page)

4.4. Documentation 51

(continued from previous page)

```
Just a string

Attributes
-----
capX: str
Capitalized x
```

or:

```
def __init__(self, x):
    """

    Demonstration class

    Parameters
    ------
    x: str
        Just a string

Attributes
    ------
    capX: str
        Capitalized x
    """
```

Deprecation

If an object is deprecated or will be modified in future versions, then the <code>deprecated()</code> and <code>willChange()</code> decorators should be applied to the object, and a note should be added to the docstring indicating as much.

4.4.2 Examples

When possible, features should be demonstrated, either through Jupyter notebooks in the examples/ directory, or with an Examples section in the docstring. Specifically, all readers should be demonstrated as Jupyter notebooks that detail the typical usage, user control settings, and examples of how the data is stored and accessed.

These Jupyer notebooks can be converted to .rst files for inclusion in the manual with the command jupyter nbconvert --to=rst.

4.5 Pull Request Checklist

Below is the criteria that will be used in the process of reviewing pull requests (PR):

- 1. The content of the PR fits within the scope of the project Scope
- 2. The code included in the PR is written in good pythonic fashion, and follows the style of the project *Coding Style*
- 3. The code directly resolves a previously raised issue Issues
- 4. PR does not cause unit tests and builds to fail
- 5. Changes are reflected in documentation *Documentation*

4.6 Version Control

This project utilizes versioneer to update the project verion based on release and commit history. Using this tool allows the project version to match **PEP 440** style versions, with minor exceptions for developer (non-public release) versions. For public releases, where sufficient changes have been made through added features, bug fixes, or wholesale changes, the version will be of the form major.release.patch. Changes in major indicate vast user-facing changes to the core functionality and/or API, while changes to release indicate a new feature added or substantial improvement that does not alter the user-facing API. In the event of bug fixes or minor tweaks, the patch number should be incremented.

For non-public releases, e.g. the develop branch, versioneer includes some additional information in the project version. Here, the version is of the form major.minor.patch[+/-]N.commit[.dirty].[+/-]N indicates that this version is N commits ahead of or behing the latest public release, and commit is the short version of the latest commit on the branch for this version. dirty will be present if the current version has uncommitted changes. This level of precision with respect to versioning allows for easy identification if people are working on multiple branches and/or having issues.

4.6.1 Releases

Releases should be done with git tags from the master branch and then pushed to GitHub. versioneer works by locating these tags in the git history, and works best with annotated tags, which can be created with:

```
git tag -a <version>
git tag -s <version>
git tag -m <msg> <version>
```

Pushing these tags to GitHub creates a new release, and shares the tag with all who have cloned the repository. If a message is used, the messages should be a brief message describing the changes on this tag. On the release page, a more detail list of changes, such as pull requests and issues closed, should be listed.

In the future, python installers such as python wheels can be built by running python setup.py bdist_wheel. These can be manually uploaded to the release page, or the python package index for users who only want the python files without examples or documentation.

4.6. Version Control 53

CHAPTER

FIVE

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

S

serpentTools.messages, 26

58 Python Module Index

INDEX

A	D
addData() (serpentTools.objects.containers.HomogUniv method), 37	data (serpentTools.objects.materials.DepletedMaterial attribute), 32
addData() (serpentTools.objects.materials.DepletedMaterial method), 33	al data (serpentTools.objects.materials.DepletedMaterialBase attribute), 31
addTallyData() (serpentTools.objects.containers.Detector method), 36	data (serpentTools.samplers.depletion.SampledDepletedMaterial attribute), 43
addUniverse() (serpent- Tools.objects.containers.BranchContainer method), 30	day (serpentTools.objects.containers.HomogUniv at- tribute), 37 days (serpentTools.objects.materials.DepletedMaterial at-
adens (serpentTools.objects.materials.DepletedMaterial attribute), 32	tribute), 32 days (serpentTools.objects.materials.DepletedMaterialBase
adens (serpentTools.objects.materials.DepletedMaterialBa attribute), 31	se attribute), 31 days (serpentTools.samplers.depletion.SampledDepletedMaterial
adens (serpentTools.samplers.depletion.SampledDepletedlattribute), 43	debug() (in module serpentTools.messages), 26
allData (serpentTools.samplers.depletion.SampledDeplete attribute), 43	Tools.objects.materials), 32
allMdata (serpentTools.samplers.depletion.DepletionSampattribute), 42	Tools.objects.materials), 31
В	DepletionReader (class in serpent- Tools.parsers.depletion), 39
b1Exp (serpentTools.objects.containers.HomogUniv attribute), 37	DepletionSampler (class in serpent- Tools.samplers.depletion), 42
b1Unc (serpentTools.objects.containers.HomogUniv attribute), 37	depmtx() (in module serpentTools.parsers), 28 deprecated() (in module serpentTools.messages), 26
BranchContainer (class in serpent-Tools.objects.containers), 30	Detector (class in serpentTools.objects.containers), 36 DetectorBase (class in serpentTools.objects.containers),
BranchingReader (class in serpent-Tools.parsers.branching), 38	DetectorReader (class in serpentTools.parsers.detector),
bu (serpentTools.objects.containers.HomogUniv attribute), 37	detectors (serpentTools.parsers.detector.DetectorReader attribute), 39
BumatReader (class in serpentTools.parsers.bumat), 38 burnup (serpentTools.objects.materials.DepletedMaterial attribute), 32	detectors (serpentTools.samplers.detector.DetectorSampler attribute), 40
burnup (serpentTools.objects.materials.DepletedMaterialB attribute), 31	as Detector Sampler (class in serpent- Tools.samplers.detector), 40
$burnup (serpent Tools. samplers. depletion. Sampled Depleted \\ attribute), 43$	E
C critical() (in module serpentTools.messages), 26	error() (in module serpentTools.messages), 26 errors (serpentTools.objects.containers.DetectorBase at- tribute), 34

errors (serpentTools.samplers.detector.SampledDetector attribute), 41 expandVariables() (serpent-	iterMaterials() (serpent- Tools.samplers.depletion.DepletionSampler method), 42
Tools.settings.UserSettingsLoader method), 25	K
F	KeywordParser (class in serpentTools.engines), 29
files (serpentTools.samplers.depletion.DepletionSampler attribute), 42 files (serpentTools.samplers.detector.DetectorSampler attribute), 40 files (serpentTools.samplers.Sampler attribute), 45 finalize() (serpentTools.samplers.SampledContainer method), 45 FissionMatrixReader (class in serpentTools.parsers.fissionMatrix), 39	L line (serpentTools.engines.KeywordParser attribute), 29 line (serpentTools.engines.PatternReader attribute), 29 loadFromContainer() (serpent- Tools.samplers.SampledContainer method), 46 loadYaml() (serpentTools.settings.UserSettingsLoader method), 25
free () (serpent Tools. samplers. depletion. Sampled Depleted Mattheward (Sampler Samplers) and the sampler of the sampler	14 <mark>/4</mark> rial
method), 43 free() (serpentTools.samplers.Sampler method), 45	map (serpentTools.samplers.depletion.DepletionSampler attribute), 42
G	map (serpentTools.samplers.detector.DetectorSampler attribute), 40
get() (serpentTools.objects.containers.HomogUniv method), 38	map (serpentTools.samplers.Sampler attribute), 45 match (serpentTools.engines.PatternReader attribute), 29
getReaderSettings() (serpent- Tools.settings.UserSettingsLoader method),	materials (serpentTools.parsers.depletion.DepletionReader attribute), 39
25 getUniv() (serpentTools.objects.containers.BranchContaine method), 30	***************************************
getValues() (serpentTools.objects.materials.DepletedMaterials	44110440), 55
method), 32 grids (serpentTools.objects.containers.DetectorBase at- tribute), 34	mdens (serpentTools.objects.materials.DepletedMaterialBase attribute), 31 mdens (serpentTools.samplers.depletion.SampledDepletedMaterial
grids (serpentTools.samplers.detector.SampledDetector attribute), 41	attribute), 43 meshPlot() (serpentTools.objects.containers.DetectorBase
Н	method), 34 metadata (serpentTools.objects.containers.HomogUniv
HomogUniv (class in serpentTools.objects.containers), 37	attribute), 37 metadata (serpentTools.parsers.depletion.DepletionReader
I	attribute), 39
indexes (serpentTools.objects.containers.DetectorBase attribute), 34	metadata (serpentTools.samplers.depletion.DepletionSampler attribute), 42
indexes (serpentTools.samplers.detector.SampledDetector attribute), 41	metadataUncs (serpent- Tools.samplers.depletion.DepletionSampler
inferReader() (in module serpentTools.parsers), 27 infExp (serpentTools.objects.containers.HomogUniv at-	attribute), 42 MismatchedContainersError, 26
tribute), 37	N
info() (in module serpentTools.messages), 26 infUnc (serpentTools.objects.containers.HomogUniv at-	name (serpentTools.objects.containers.HomogUniv at-
tribute), 37 iterBranches() (serpent-	tribute), 37 names (serpentTools.objects.materials.DepletedMaterial
Tools.parsers.branching.BranchingReader method), 38	attribute), 32 names (serpentTools.objects.materials.DepletedMaterialBase attribute), 31

60 Index

names (serpentTools.samplers.depletion.SampledDepletedNattribute), 43	Visitating (serpentTools.samplers.depletion.DepletionSampler attribute)
0	settings (serpentTools.samplers.detector.DetectorSampler attribute), 40
orderedUniv (serpentTools.objects.containers.BranchContaattribute), 31	
P	slice() (serpentTools.objects.containers.DetectorBase
parse() (serpentTools.engines.KeywordParser method), 29	method), 35 spectrumPlot() (serpent-
parsers (serpentTools.samplers.depletion.DepletionSampler attribute), 42	method), 35
parsers (serpentTools.samplers.detector.DetectorSampler attribute), 40	spreadPlot() (serpentTools.samplers.depletion.SampledDepletedMaterial method), 44
parsers (serpentTools.samplers.Sampler attribute), 45 PatternReader (class in serpentTools.engines), 29	spreadPlot() (serpentTools.samplers.detector.SampledDetector method), 41
plot() (serpentTools.objects.containers.DetectorBase method), 35	stateData (serpentTools.objects.containers.BranchContainer attribute), 30
plot() (serpentTools.objects.materials.DepletedMaterial method), 33	step (serpentTools.objects.containers.HomogUniv attribute), 37
plot() (serpentTools.samplers.depletion.SampledDepletedM method), 43	la te rial
process() (serpentTools.samplers.Sampler method), 45 Python Enhancement Proposals PEP 257, 50 PEP 440, 53	tallies (serpentTools.objects.containers.DetectorBase attribute), 34 tallies (serpentTools.samplers.detector.SampledDetector attribute), 41
PEP 8, 49	U
R	uncertainties (serpentTools.samplers.depletion.SampledDepletedMaterial
read() (in module serpentTools.parsers), 27 read() (serpentTools.samplers.Sampler method), 45 reshape() (serpentTools.objects.containers.Detector method), 36 ResultsReader (class in serpentTools.parsers.results), 40	attribute), 43 universes (serpentTools.objects.containers.BranchContainer attribute), 30 updateLevel() (in module serpentTools.messages), 26 UserSettingsLoader (class in serpentTools.settings), 25
S	W
SampledContainer (class in serpentTools.samplers), 45 SampledDepletedMaterial (class in serpent- Tools.samplers.depletion), 42 SampledDetector (class in serpent-	warning() (in module serpentTools.messages), 26 willChange() (in module serpentTools.messages), 26 Y
Tools.samplers.detector), 40 Sampler (class in serpentTools.samplers), 45	yieldChunks() (serpentTools.engines.KeywordParser method), 29
SamplerError, 26 scores (serpentTools.objects.containers.DetectorBase at- tribute), 34	yieldMatches() (serpentTools.engines.PatternReader method), 29
scores (serpentTools.samplers.detector.SampledDetector attribute), 41	Z zai (serpentTools.objects.materials.DepletedMaterial at-
searchFor() (serpentTools.engines.PatternReader method), 29	tribute), 32 zai (serpentTools.objects.materials.DepletedMaterialBase
serpentTools.messages (module), 26 SerpentToolsException, 26	attribute), 31
settings (serpentTools.parsers.depletion.DepletionReader attribute), 39	zai (serpentTools.samplers.depletion.SampledDepletedMaterial attribute), 43

Index 61